

Unattended Upgrades

To configure linux hosts to automatically install updates and upgrades, add or edit the following lines in `/etc/apt/apt.conf.d/50unattended-upgrades`. Feel free to change the settings as you see fit.

```
Unattended-Upgrade::Mail "user@example.com";
Unattended-Upgrade::MailOnlyOnError "true";
Unattended-Upgrade::Remove-Unused-Kernel-Packages "true";
Unattended-Upgrade::Remove-Unused-Dependencies "true";
Unattended-Upgrade::Automatic-Reboot "true";
Unattended-Upgrade::Automatic-Reboot-Time "02:38";
```

At the top of `/etc/apt/apt.conf.d/50unattended-upgrades`, you'll notice the block below, be sure to follow my comments and make the changes needed

```
Unattended-Upgrade::Allowed-Origins {
    "${distro_id}:${distro_codename}";
    "${distro_id}:${distro_codename}-security";
    // Extended Security Maintenance; doesn't necessarily exist for
    // every release and this system may not have it installed, but if
    // available, the policy for updates is such that unattended-upgrades
    // should also install from here by default.
    "${distro_id}ESM:${distro_codename}";
    "${distro_id}:${distro_codename}-updates"; // <-- Uncomment this line.
    // "${distro_id}:${distro_codename}-proposed";
    // "${distro_id}:${distro_codename}-backports";
};
```

Add the following lines to `sudo vim /etc/apt/apt.conf.d/20auto-upgrades`.

```
APT::Periodic::Update-Package-Lists "1";
APT::Periodic::Unattended-Upgrade "1";
# Add these two lines...
APT::Periodic::Download-Upgradeable-Packages "1";
APT::Periodic::AutocleanInterval "7";
```

Test that you can run a dry-run update using unattended-upgrades -

```
sudo unattended-upgrades --dry-run --debug
```

Also, check the logs for unattended-upgrades below

```
less /var/log/unattended-upgrades/unattended-upgrades.log
```

Revision #3

Created 7 September 2019 07:43:50 by Shaun Reed

Updated 18 December 2021 16:37:39 by Shaun Reed